

Function FK - PF Key Definition

This function allows you to assign commands to PF keys in the various Com-plete utilities. Pressing a PF key in the utility has the same effect as if you had entered the assigned command in the command line. If you select the FK option from the utility menu, the list of utilities for which you are authorized is displayed, for example:

16:38:51	TID	6	COM-5.1.	User	SAGAWW	05/07/97
System: Lcl 8	---	PF-Key Maintenance	---			UPF0
Nbr Utility	Nbr Utility	Nbr Utility	Nbr Utility	Nbr Utility	Nbr Utility	
---	---	---	---	---	---	
1 COM-PASS	13	25	37	49		
2 UQ	14	26	38	50		
3 UPDS	15	27	39	51		
4 USTOR	16	28	40	52		
5 UDUMP	17	29	41	53		
6	18	30	42	54		
7	19	31	43	55		
8	20	32	44	56		
9	21	33	45	57		
10	22	34	46	58		
11	23	35	47	59		
12	24	36	48	60		
Please select Utility number..: 0						
and System Id.....:						
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---						
End Updat						

Select the utility for which you wish to define PF Keys by typing the number in the *Utility Number* input field.

If you have multiple Com-pletes installed, and you do not enter data into the *System ID* field, your Global PF Key definitions for the specified utility are defined. If you require special PF Key definitions for one Com-plete system only, enter its ID in this field (in the above example, the current Com-plete system has an ID of 8).

When you press ENTER, the PF definition screen is displayed, for example for UQ (no system ID specified):

```

14:19:49      TID    11      COM-5.1      User SAGAWW      23.11.97
System: Global                                UPF1

                        Dynamic PF-Key Table
                        UQ      (Private)

PFnr Command                                Dis-
-----
PF01
PF02
PF03
PF04
PF05
PF06
PF07
PF08
PF09
PF10
PF11
PF12
-----

      Override undefined keys with system default keys: N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--
      Mode  End      Updat      bwd      fwd      Purge      Quit

```

You can enter or modify data in the input fields. Meaning of the fields according to column header:

Column	Meaning
Command	<p>The command to be executed when you press the PF Key. Valid commands are: Com-plete control functions. Com-plete commands, optionally with parameters, to execute a utility program, for example:</p> <p>*UQ Q,JB=name,RR=105=UEDIT PC(COMSM1)</p> <p>Program-specific commands. For example, for UQ:</p> <p>A,RR=3</p> <p>If the required command string exceeds 64 characters, press PF2. This displays the screen in which you can enter up to 79 characters for each command string.</p>
Display	<p>Enter any character here to cause the assigned command to be displayed in the command line when the PF key is pressed. You can then modify the displayed command before you press ENTER to execute it. If you use underscore characters in the assigned command string, the cursor is placed on the first underscore when it is displayed.</p>
>	<p>An asterisk (*) is automatically displayed in this column if you have entered more than 64 characters in the command string using PF2.</p>

Press PF5 to save the definitions. Press PF3 to leave this function.